# Core Service Quick Start Guide

Last change: 17.12.2019





2 Label Family Introduction	
2.1 General Key Features	
2.2 The G1 label family	
2.3 The VUSION label family	
3 Get the latest software and documentation	
3.1 Install software	
3.2 System requirements	
3.3 Installation process	
3.4 SES-imagotag Customer and Partner Portal	
4 Core Appliance	
4.1 Why is it needed in the Store?	
4.2 Key Features	
5 Core Appliance initial setup	
5.1 USB device configuration	10
5.2 Front side LED description	11
5.3 Additional documentation	11
6 Start SES-imagotag Core Service and SES-imagotag Control Center	12
6.1 Starting SES-imagotag Core Service	12
6.1.1 Example articles	12
6.2 Starting SES-imagotag Control Center	13
6.2.1 SES-imagotag Control Center Login	13
6.3 Activating your license	14
7 ESL Access Point Configuration	
7.1 Connect and configure AP-2010	16
7.1.1 Connect and configure	16
7.1.2 Discover the Access Point	16
7.1.3 Necessary configuration on the AP-2010 web UI	17
7.1.4 The Status LED	18
7.2 Adding AP-2010 to ESL system	19
7.2.1 SES-imagotag Core Service	19
7.2.2 Jeegy Cloud/Jeegy S3	20
8 Selecting channels	
9 Setup Security	
9.1 General encryption features and how does it work	
9.2 Set the encryption key	
10 Register labels	
·	
10.2 What's on the label?	
10.2.1 Registration page vs. Reset page	
10.3Handheld terminals, USB barcode scanner and SES-imagotag Core Service iOS-App	
10.4 Encryption status	
10.5 Unlocking labels	
i i Otalit tayyiliy	




11.1 What can I do now?	27
11.2 Sending pictures to labels	27
11.3 Article management	27
11.4 Matchings/Multi-Facing	28
11.5 Set (extended) filters for enums	29
11.5.1 Extended filter operators	29
12 Templates	
12.1 General information about templates	31
12.2 SES-imagotag Template Editor	31
12.2.1 Starting SES-imagotag Template Editor	31
12.2.2 Open default template file and load records from server:	32
12.2.3 Design Mode	33
12.2.4 Enable and show color red	34
12.2.5 Help Content	34
13 Integration	35
13.1 Webservice integration	
13.2 Plugins	35
13.3 Custom integration	35
14 Troubleshooting	36
14.1 SES-imagotag Core Service Dashboard	
14.2 Running the SES-imagotag Core Service as a background service	37
14.3 Where can get a demo/development license key?	37
14.4 Deleting the demo articles	37
14.5 Establish a network configuration when no DHCP is available – Step by step	38
14.6 Access point discovering with Bonjour Services	38
14.7 What can I do if the Status LED of the AP-2010 access point doesn't turn blue?	38
14.8 Labels don't come online	39
14.9 The encryption does not work	39
14.10 Unlocking labels	39
14.11 Starting Java applications	39
14.12 Encoding problems	40
14.13 Reserve RAM for Java heap space	40
14.14 Further documentation	41
15 Declaration	
16 Warning	45



# 1 Electronic Shelf Labeling – A brief introduction

An electronic shelf label is a device that shows article data and price information on its display. In comparison to printed labels the information is automatically updated if price or article data changes.



- Cost reduction through elimination of manual price changes
- Fully automatic price updates from the headquarters to the branch stores within seconds
- Process security and price integrity – 100% correlation between cash point and shelf
- Increased flexibility in price design and immediate reaction to market situation Image gain due to use of highly modern technology
- Simplified processes for store personnel
- Enhanced sales & price profitability maximize price performance and profit opportunities



# 2 Label Family Introduction

The SES-imagotag electronic shelf label family offers high-quality display options, operating with a replaceable battery, thus working without any external power supply.

The performance of the labels (updates per hour) depends on the mode of the access point. In the USA and Canada the AP-2010 usa/canada bundle incl. antenna with limited data efficiency is required (based on the FCC/IC regulation).

# 2.1 General Key Features

- 2.4 GHz proprietary radio protocol
- Radio coverage: up to 25 meters
- · Bi-directional communication
- 11 available communication channels
- Ultra-low power consumption
- Customer-replaceable battery
- Full graphical e-Ink display with paper-like readability
- Different configurations available (theft protection, display protection, LED flash)
- · Label versions for deep-freezing environments
- Super wide viewing angle (nearly 180 degrees)
- · Flexible mounting options available
- · May be used in landscape and portrait mode
- Fast response time (less than 15/30 seconds, depends on wakeup time)
- 128-bit AES encryption with secure key exchange
- Multiple pages support with preloading and fast page switching
- Integrated "Active" NFC
- Integrated Passive NFC tag
- Integrated NFC
  - G1 Passive NFC
  - VUSION "Active" NFC

# 2.2 The G1 label family

The SES-imagotag G1 BWR label family is capable of changing all pixels to black, white or red. The current line-up has display sizes from 1.6 inch to 12.2 inch.

Caption	Display Res- olution	Density (dpi)	Display Colors	Useable Pages	Active Dis- play Area (mm)	Updates/hour/AP (standard / FCC&IC mode)	Battery life- time: 5 years with N updates per day
G1 1.6 BWR NFC	152 x 152	140	b/w/r	4*	27.5 x 27.5	7500/4600	1
G1 2.2 BWR NFC / Bossard 2.2 red NFC	212 x 104	111	b/w/r	4*	48.6 x 23.8	8500/5000	2
G1 2.6 BWR NFC	296 x 152	125	b/w/r	4*	60.1 x 30.7	4500/2600	2
G1 2.7 BW NFC	264 x 176	117	b/w	8*	57.3 x 38.2	5000/2700	4
G1 2.7 BWR NFC	264 x 176	117	b/w/r	4*	57.3 x 38.2	4500	2
G1 4.2 BW NFC	400 x 300	120	b/w	4*	84.8 x 63.6	3000/1600	4
G1 4.2 BWR NFC	400 x 300	120	b/w/r	4*	84.8 x 63.6	2000/1300	2
G1 4.5 BWR NFC	480 x 176	117	b/w/r	4*	104.2 x 38.2	2500/1500	2
G1 6.0 BWR NFC	600 x 448	129	b/w/r	4*	114.9 x 85.8	900/500	2
G1 7.4 BW NFC	480 x 800	126	b/w	12*	97 x 161.6	1000/500	8
G1 7.4 BWR NFC	480 x 800	126	b/w/r	4*	97 x 161.6	600/300	2
S-tag 6 HF NFC	-	-	b/w	4	53 x 19.3	20000/20000	4



\*One useable page is shared with the registration code page. This page is initially shown when the label is shipped. After registration this page can be used as a custom page. To restore the original content a service utility is required. To prevent accidentials overwrite this page is protected. To unlock this page contact the SES-imagotag support team.

The content of all pages except page number 0 won't remain after a firmware update.

# 2.3 The VUSION label family

The SES-imagotag VUSION (2.4GHz) electronic shelf label family is capable of changing all pixels to black, white or red. The current line-up has display sizes from 1.6 inch to 12.2 inch. They may be used in landscape and portrait mode and can be configured in terms of radio, theft protection, display protection and LED flash.

Caption	Model	Display Res- olution	Density (dpi)	Display Colors	Useable Pages	Active Display Area (mm)	Updates/hour/AP (standard / FCC&IC mode)	Battery lifetime: 5 years with N updates per day
VUSION 1.6	EDG2-0160-A	152 x 152	140	b/w/r	4	27.5 x 27.5	7500/4600	1
VUSION 2.2	EDG2-0220-A EDG3-0220-A	212 x 104	111	b/w/r	4	48.6 x 23.8	8500/5000	2
VUSION 2.2 F	EDG2-0220-A	212 x 104	111	b/w	4	48.6 x 23.8	10000/6500	1*
VUSION 2.6	EDG2-0260-A	296 x 152	125	b/w/r	4	60.1 x 30.7	4500/2600	2
VUSION 2.6 F	EDG2-0260-A	296 x 152	125	b/w	4	60.1 x 30.7	6500/4500	1*
VUSION 2.7	EDG2-0270-A EDG2-0270-B	264 × 176	117	b/w/r	4	57.3 x 38.2	4500/2600	2
VUSION 3.7	EDG2-0370-A	416 x 240	130	b/w/r	4	81.54 x 47.04	2000/1300	2
VUSION 4.2	EDG2-0420-A	400 x 300	120	b/w/r	4	84.8 x 63.6	2000/1300	2
VUSION 4.5	EDG2-0450-A	480 x 176	117	b/w/r	4	104.2 x 38.2	2500/1500	2
VUSION 5.9	EDG2-0590-A	720 x 256	134	b/w/r	4	138.96 x 49.40	1100/550	2
VUSION 7.4	EDG2-0740-A	480 x 800	126	b/w/r	4	97 x 161.6	600/300	2
VUSION 9.7	EDG2-0970-A	960 x 672	121	b/w/r	4	201.60 x 141.12	300/150	2
VUSION 12.2	EDG2-1220-A	768 x 960	103	b/w/r	6	190.08 x 237.6	300/150	1

<sup>\*</sup> Battery lifetime: 3 years with N updates per day

The content of all pages except page number 0 won't remain after a firmware update.



### 3 Get the latest software and documentation

Register at the SES-imagotag Customer and Partner Portal to get access to the latest software and documentation.

https://portal.imagotag.com

### 3.1 Install software

There's several software you'll have to install in order to configure and setup your ESL system. You'll just have to extract the following 3 archives in a location of your choice:

- 1. SES-imagotag Core Service <server.zip>
- 2. SES-imagotag Control Center <cli>client.zip>
- 3. SES-imagotag Template Editor <template.zip>

### 3.2 System requirements

- Server hardware: Pentium 4 (2 GHz or higher), 2 GB RAM
- Java Runtime Environment Version 6, Update 36 or higher
- Windows 7, Windows 10, Windows Server 2008 (R2), Windows Server 2012, Windows Server 2016, Suse Enterprise Linux 11, Ubuntu 12 (all 32/64-bit versions), Mac OS X
- SES-imagotag Core Service
- SES-imagotag Access Point(s)
- SES-imagotag Label(s)
- · License key

# 3.3 Installation process

Please unpack the zip-archives <server.zip>, <client.zip> and <template.zip> on your machine - e.g. under C:\ses-imagotag-core-service\.

**Note:** To unpack the zip-files you can either use the windows internal archive-unpacker (see screenshots) or an unpack tool of your choice (e.g. the free tool 7zip – www.7zip.org).




FIGURE 1-2: Unpack/Install imagotag Software #1

After unpacking all 3 archives, your folder should look something like this:






FIGURE 1-3: Unpacked imagotag software folder

The SES-imagotag Core Service is now installed and you can step forward to point see *Start SES-imagotag Core Service and SES-imagotag Control Center* on page 12.

# 3.4 SES-imagotag Customer and Partner Portal

After user registration and activation you will have access to documentation.

You can activate, manage and download your SES-imagotag software licenses see *Start SES-imagotag Core Service and SES-imagotag Control Center* on page 12.

Your user account will not be assigned to a customer account yet. Ask our sales backoffice team for user assignment (sales.at@ses-imagotag.com).



# 4 Core Appliance

The Core Appliance is a compact network device which can be used to run the SES-imagotag Core Service in the store, instead of using an additional dedicated server. The SES-imagotag Core Service is always needed in the store locally, also when cloud-based/centralized middleware systems like Jeegy S3 Centralized/Jeegy Cloud or Bison ESL Manager is used.

### 4.1 Why is it needed in the Store?

- Continuous communication with access points and labels is required (even without tasks)
- Limited bandwidth between store and headquarters
- Disconnected VPN connection will prevent proper operation
- Load (image rendering...) is distributed to stores

# 4.2 Key Features

- Core Appliance is optimized to run up to 30 000 labels and 7 access points
- Easier and faster shop installations ("Plug and Play")
- · Is not recognized as an additional server
- · Low maintenance
- Easy replace/restore when hardware crashes
- Limited deployment variabilities
- · Lower development costs
- · Lower support costs
- · Better brand recognition
- Easier to sell as a "solution in a box"
- · Less overall risk for system integrators





# 5 Core Appliance initial setup

To operate the Core Appliance there are only a few steps necessary:

- 1. Supply with power
- 2. Turn it on (button on the backside of the device)
- 3. Plug it into your network
- 4. Initial setup
- 5. Update to the latest version

Per default, the Core Appliance comes with DHCP enabled. So if you have a DHCP service running you can find it with the MAC address which is printed on the bottom side of the Core Appliance.

If there's no way to get access to the DHCP server we recommend to use an USB device with a configuration file to configure the appliance initially.




FIGURE 1-4: Core Appliance rear view

# 5.1 USB device configuration

You can find an example configuration file (**example.config**) at ourSES-imagotag Customer and Partner Portal.

Core Appliance service reference mode | Core Appliance example.config file

After downloading, editing and copying the configuration file onto any USB device, the configuration is automatically adopted after plugging in the USB flash drive into the Core Appliance. A triple beep indicates the successful configuration. A single beep signals that the configuration hasn't been set successful.

The web user interface of the Core Appliance is now available under http://<ip-address>.

The initial configuration of the Core Appliance can be compared with the installation and start of an SES-imagotag Core Service. After configuration, you can access the Core Appliance via the SES-imagotag Control Center from every system connected to your network (see *Start SES-imagotag Core Service and SES-imagotag Control Center* on page 12).

### Example.config file

To set up your Core Appliance for the first run you'll have to set at least the following network parameters:

- · IP address
- Subnet mask
- Optional: Gateway, DNS

To set the parameters mentioned above the contents of the configuration file might look like this:

```
# Set IP address of bridge interface
set network br0 192.168.1.100 255.255.255.0
# Set a gateway
set gateway 192.168.1.1
```





```
# Set a nameserver
set dns 192.168.1.21
```


**Note**: This simple bridge configuration connects the network interfaces. No matter where the network cable is plugged in, the appliance is accessible via the configured bridge address.

### 5.2 Front side LED description

On the front side of the appliance you can see several status information:



Core Appliance front view LED status information (Core Appliance version 1.8.0 or higher)



### 5.3 Additional documentation

You can find additional documentation regarding the Core Appliance (e.g. a complete service mode reference) on our SES-imagotag Customer and Partner Portal.



# 6 Start SES-imagotag Core Service and SES-imagotag Control Center

### 6.1 Starting SES-imagotag Core Service

If you've recently configured yourCore Appliance the SES-imagotag Core Service software is already running and you can step forward to the next step.

In order to start the SES-imagotag Core Service with the default configuration, just execute the jar file "server.jar" as described in *Troubleshooting* and wait for the small service GUI to show up (if the window doesn't show up after all, make sure your Java installation and configuration is correct).




FIGURE 1-5: Core Service web UI



The SES-imagotag Core Service will listen to TCP connections on Port 8000 and 8001 and UDP connections on Port 8000. Please make sure that there is no firewall issue and/or interference with other systems.

After start of the SES-imagotag Core Service you can check the web user interface:

URL: http://<host|ip>:8000 Login: admin/admin

During the first start the SES-imagotag Core Service will automatically create a Derby<sup>1</sup> database. If another database connection is needed or preferred, the connection parameters should be validated by SES-imagotag GmbH.

**Note:** As you can see there are several level numbers. You can find the description of the different levels in the Developer Reference (which is also part of the documentation available at the SES-imagotag Customer and Partner Portal) under "Integration Levels".

### 6.1.1 Example articles

For easier usage some example articles can be preloaded at the time you start the SES-imagotag Core Service. You can find the corresponding XML article data here: C:\ses-imagotag-core-service\server\data\fixtures\.

To enable and disable the preloading of these fixtures go to the system configuration and set the corresponding property "importFixtures" true or false.

**Note:** The article records are based on the XML-standard.

<sup>&</sup>lt;sup>1</sup>Apache Derby, an Apache DB subproject, is an open source relational database implemented entirely in Java





# 6.2 Starting SES-imagotag Control Center

Go to the extracted directory and execute the "client.jar" file.




FIGURE 1-6: Starting SES-imagotag Control Center

The SES-imagotag Control Centeris configured to connect to a server on the local machine per default. In order to change this to a remote machine in a network you have to start the SES-imagotag Control Center with an additional parameter:

### **Windows**

- Create a shortcut/Edit existing short cut
- Right click to the shortcut and select "Properties"
- Append "--host hostnameOrIPAddress" at the end of the "Target" field. (Note: The text to append starts with an space and there are 2 hyphens to add!)

### Linux

 Append "--host hostnameOrIPAddress" at the end of command (e.g. "java -jar client.jar --host 192.168.1.100" Note: The text to append starts with an space and there are 2 hyphens to add!)




FIGURE 1-7: Starting SES-imagotag Control Center with parameter

### 6.2.1 SES-imagotag Control Center Login

Username: adminPassword: admin






FIGURE 1-8: SES-imagotag Control Center Login

# 6.3 Activating your license

After starting the SES-imagotag Core Service and SES-imagotag Control Center it's necessary to activate the license key which is included in the "Software License Document". To view your current license status there's a License status dialog. You can find it in the SES-imagotag Control Center under "Help - License status". Since no license is activated/imported yet the window should look similar to this:




FIGURE 1-9: License Status Dialog

Copy the "System serial" to the clipboard (STRG+C or right click "Copy to clipboard") and then click the "License activation". You'll be automatically redirected to the SES-imagotag Customer and Partner Portal https://portal.imagotag.com.

Please **log in** (or register a new user). After log in, you can see a summary of already activated licenses and/or activate a new license. Click **"activate new license"**.

Fill in "License key", copy/paste the "System serial" (from the "License Status" dialog), add a Comment (optional) and click the "Activate" button.



# **Activate License**

This will generate an activated license file from a license key. The license is locked to the activated system and cannot be used with other systems.

Hint: To find your system serial open the dialog "Help — License Status" from the menu in the ESL Client or open "Maintenance — Status — License Status" in the web management interface of the ESL Server.

### **New License Activation**



© SES-imagotag GmbH, 2018

### FIGURE 1-10: Activate License (SES-imagotag Customer and Partner Portal)

Download the generated license file and complete the licensing process by importing the license file to your ESL system. With the successful activation of your license you're now able to register labels and add ESL access points.




FIGURE 1-11: Import of license file downloaded before

**Note:** Press "F5" (after 15 seconds) to update the license status after license file import.



# 7 ESL Access Point Configuration

The ESL access points are the communication center in the store that transmits information to the labels. In order to ensure the communication between SES-imagotag Core Service, ESL access point(s) and the labels the access points have to be configured at the start of the SES-imagotag Core Service.

In the Core Service Quick Start Guide you will find the procedure to connect and configure the SES-imagotag AP-2010. For other ESL access point(s) and SES-imagotag Retail IoT Connectors, please find on the SES-imagotag Customer and Partner Portal the corresponding Configuration Guide.

### 7.1 Connect and configure AP-2010

### 7.1.1 Connect and configure

Before labels are able to communication with the SES-imagotag Core Service at least one ESL access point needs to be configured. In standard configuration the AP-2010 gets an IP-address via DHCP (recommended) and is accessible via imagotag AP-2010 web UI:

URL: http://<host|ip>:8080 Login: admin/admin

Important Note: In this part of the Core Service Quick Start Guide it is assumed that a DHCP server is present (you can find the steps to discover the access point without DHCP in the Troubleshooting section - see Establish a network configuration when no DHCP is available – Step by step on page 38

### 7.1.2 Discover the Access Point

Before you can configure the AP-2010 access point it's necessary that it will be discovered.

The following points have to be observed:

- Connect your machine to the same network as the AP
- · Plug in the power supply of the access point
- During the boot process of the access point, start the SES-imagotag Core Service software on the computer
- When the access point is up (LED turns orange), the SES-imagotag Core Service will discover it with an IP address (Note: The discovering process may take up to 2 minutes)
- Use the SES-imagotag Control Center to connect to your SES-imagotag Core Service
- Under System Access Point Status the AP should be listed as discovered (after successful boot sequence)




FIGURE 1-12: List of discovered ESL access points

Now you're able to configure the AP-2010 access point via AP-2010 web UI under <a href="http://<DHCP-IP-address">http://<DHCP-IP-address</a> or a right click on the discovered AP -> Open in browser....

In the status overview you get some details about the AP-2010:




FIGURE 1-13: AP-2010 Status overview


It's recommended for the demo installation not to use the "Centralized Configuration" feature and configure the AP manually.

### 7.1.3 Necessary configuration on the AP-2010 web UI


The following actions need to be performed over the AP-2010 web UI




1. Deactivate Centralized Configuration: Administration -> Configuration Mode



2. Set up network details (or keep DHCP mode): Administration -> Network



3. Set up an ESL channel: Administration -> Wireless Channel





The AP-2010 supports 11 ESL channels. It's recommended to **choose one of the recommended channels: 3, 5, 8, 9 or 10**. These channels do not interfere with standard Wi-Fi channels 1, 6, 11 and are scanned by the labels more often.

### 7.1.4 The Status LED

There are several LED colors that indicates the status of the AP-2010.



Color	Description	Note
Red	Boot process	Can take up to 5 minutes, if it takes much longer, the device is defective and there is a need for service.
Blue	Operation mode	AP-2010 is configured in any Core Service, has an ESL channel set and the has successfully received the roaming table from the Core Service
Orange	Ready for operation	Operational, but not connected to any ESL system, no ESL channel is set, a service on the AP-2010 failed to start, AP-2010 has not received the roaming table yet
Red (blinking)	Running Firmware Update	During this time there is no connection to the electronic label

If there are any problems regarding the ESL access point please see chapter see *Troubleshooting* on page 36.

# 7.2 Adding AP-2010 to ESL system

### 7.2.1 SES-imagotag Core Service

After the configuration in the AP-2010 web UI it's necessary to add the AP-2010 via the SES-imagotag Control Center: System – Access Point Configuration – New ... or right click on a discovered ESL access point - Create configuration.

After saving the AP configuration you should see the AP under System – Access Point Status as ONLINE. In addition the AP status LED should turn BLUE.




FIGURE 1-14: SES-imagotag Control Center System - Access Point Status - Create configuration

If the ESL access point is not discovered or if there is no DHCP server available you have to add the AP-2010 manually. When creating a new access point configuration under System - Access Point Configuratio, select "Manual Configuration" (if you don't use Centralized Configuration) and enter Access Point ID (AP ID), IP address and port (Host).




FIGURE 1-15: SES-imagotag Control Center System - Access Point Configuration - Create configuration

**Note**: It is possible to configure the access point via host name. To get this working there has to be a corresponding entry in the DNS sever.

### 7.2.2 Jeegy Cloud/Jeegy S3

Add the AP-2010 in Jeegy Cloud/Jeegy S3 under Transmission system - High Frequency manually or by using the auto-register function. If you want to use the access point in DHCP mode, use only the AP ID for adding the AP-2010. When the auto-register function is activated, the AP-2010 will added automatically with AP ID only.




FIGURE 1-16: Adding access point in Jeegy Cloud/Jeegy S3



# 8 Selecting channels

For a working installation an ESL channel must be selected on each ESL access point in the network. There are 11 non overlapping ESL channels reserved for the communication with the labels. Five of these ESL channels do not interfere with typical Wi-Fi installations and should therefore be favored. These are the ESL channels 3, 5, 8, 9 and 10 and they should be selected if there is a Wi-Fi installation on the Wi-Fi channels 1, 6 and 11.




FIGURE 1-17: Comparison between common used Wi-Fi and ESL channels

If there is a Wi-Fi installation operating at 2.4 GHz (IEEE 802.11 b/g/n) or any other radio frequency (RF) technology that uses the 2.4 GHz ISM band make sure to select the ESL channels that are least overlapping with the existing installation. If there is no ESL channel without any overlapping both the ESL and existing installation should still work but there might be a reduced overall speed in both installations.

**Warning**: Do not select the same ESL channel on two access points within one area. This will cause interferences and avoids labels from joining the network or being updated. The same ESL channel may only be selected on two access points if it can be guaranteed that every label is within the range of only one of these access points.



# 9 Setup Security

The security concept is based on individual registration codes for each label. Not only that the new concept simplifies installations, it also provides stronger encryption and a secure key exchange with individual communication key derived from a user defined network key.

## 9.1 General encryption features and how does it work

- · Solid improved safety
- Encrypted data type AES128 (Advanced Encryption Standard)
- User defined 128 bit network key for each installation
- Key is distributed to labels automatically

The system requires a user defined 128 bit network key for each installation. The key is derived from a passphrase that is defined by the customer and stored in the SES-imagotag Core Service and used by all ESL access points connected to that SES-imagotag Core Service to encrypt data communication to the labels.

A per-label communication key is transmitted to the labels during the registration of them. Each label is assigned an individual registration code (it combines label ID and PIN code and it's an alphanumeric case-sensitive code with 11 characters). The SES-imagotag Core Service will than automatically start the key exchange with the label secured by the PIN extracted from the registration code.

# 9.2 Set the encryption key

First step is to set the parameter "encryptionPassphrase" under System – Configuration (you can choose the encryption passphrase on your own).




FIGURE 1-18: Set encryption key

**Note:** Do not change encryption passphrase if labels are already connected and encrypted (if you want to change the encryption passphrase you'll first have to unlock all labels – see *Troubleshooting* on page 36).



# 10 Register labels

In order that labels can join the network it is necessary to register them first.

### 10.1 General procedure

Via the SES-imagotag Control Center under File – Register Labels it's possible to register your labels manually with the registration code shown on each single label or you could import a CSV file with your registration codes.

Important Note: After the registration it could last a certain time until all registered labels are joined to the network (from 30 minutes up to two hours, depending on configured ESL channels). After this you can send images to each label (see *Start tagging* on page 27).




FIGURE 1-19: Add/Delete Label and refresh entries

### 10.2 What's on the label?


All labels will arrive with its registration code (11-digit alphanumeric) shown on the display of the label. The code is printed as a 2D QR code, as a 1D Code128 barcode and as human readable text. The registration process for the customer is easy – he has only to scan one of the barcodes. The SES-imagotag Core Service will than automatically start the key exchange with the label secured by the PIN extracted from the registration code.

The two relevant codes:

- The label ID (8-digit hexadecimal) to identify the label (it's also the radio address which is similar to a MAC address).
- 2. The **registration code (11-digit alphanumeric)** is required to activate the encryption. This code also contains the label ID and a random PIN code.



### 10.2.1 Registration page vs. Reset page



The sticker (on the bottom and on the back) always contain only the label ID and therefore should not be used for registration if the encryption will be used. They are only intended for the later article assignment (matching process).

Here you can see the registration dialog in the SES-imagotag Control Center where one single label has been entered with the registration code (Pin = yes - security enabled) and the other one with the label ID (for old label versions < 3.0.0, Pin = no, no secured communication).




FIGURE 1-20: Register labels dialog (registered with registration code and label ID)



**Note:** New versions of the SES-imagotag Core Service, SES-imagotag Control Center and AP-2010 (≥ 1.3.0) will also support old labels that do not come with a pre-programmed PIN code. New labels (≥ 3.0.0) will also work in old installations together with old labels but the SES-imagotag Core Service will not accept registration codes during the registration process. To register the labels it is required to scan the barcode with the label ID from the backside or the bottom edge of the label. As the SES-imagotag Core Service will not start the key exchange all data is transmitted unencrypted to the labels.


# 10.3 Handheld terminals, USB barcode scanner and SES-imagotag Core Service iOS-App

It's also possible to register labels with a commercial USB barcode scanner (2D/1D). You can also use the SES-imagotag Core Service iOS-App (for iPhone and iPod touch [only available on request]).

Handheld terminals are mobile devices that are used to manage the ESL installation. If the handheld provides a barcode scanner, it may be used easily to link articles and labels by scanning the article barcode (usually EAN, UPC or GTIN) and the unique ID of the label.

Here you can see some screenshots of our SES-imagotag Core Service iOS-App:








FIGURE 1-21: ESL-App Home-Screen

FIGURE 1-22: ESL-App Registration FIGURE 1-23: ESL-App Matching Page Page

# 10.4 Encryption status

Here are the encryption status a label could have:

- AES: Communication with label is encrypted with 128 bit AES
- No PIN: Could not set encryption key as no PIN (registration code) was provided
  - Solution: Re-register label with registration code
- Key unset: Communication is NOT yet encrypted
  - Solution: Set encryption passphrase and ping the label to start the encryption process
- **Unsupported:** Encryption is not supported by label firmware
- Unknown: Security status is not determined yet




FIGURE 1-24: Encryption status

# 10.5 Unlocking labels

If the label was registered and a communication key was set it will no longer work in other networks using a different network key passphrase. To unlock this labels for other networks an unlock code is required. The unlock code is similar to the registration code - it is a combination of the label ID and a 128 bit PUK code.

Via SES-imagotag Control Center select File - Unlock labels and enter the unlock key.




FIGURE 1-25: Unlock Labels Dialog



# 11 Start tagging

### 11.1 What can I do now?

As soon as labels are online you can do several things:

Send images to labels, assign tags, show the current images, ping labels, reset labels (reset display to show label ID and label ID barcode), refresh displays, switch to a preloaded page, create a new matching (or multi-matching/multi-facing), set (extended) filters, check update logs, ...

### 11.2 Sending pictures to labels

- 1. Right click on one or more labels -> Send image...
- 2. Select a picture (Note: Display size must match the resolution of the image)
  - A. In the right pane, a priority (currently not relevant) could be set for the task, as well as the page to which the image should be sent and whether the image is preloaded.
  - B. If preloaded, the image is placed in the memory of the label, but not yet displayed. The image change will only be performed after the change to the relevant page. This allows for each label that images are cached on the various pages and be accessed quickly by switching to the relevant page.
- 3. By clicking on "open" the corresponding task(s) for the label(s) will be created and the transfer begins.

# 11.3 Article management

For complete management of your articles select **Articles – All Articles** in the SES-imagotag Control Center. Here you're able to create/delete and edit your articles.

The Smart Box Package comes with some predefined articles which you can see here. You can add some more demo articles, edit the existing ones or just step further to the next point Matchings.




FIGURE 1-26: Article management



# 11.4 Matchings/Multi-Facing

The logical link between articles and the label that shows the article information and price of this articles is called matching. With a matching the layout of the image rendered for the label is also defined by specifying the name of a template.

In a more technical way a matching is the triple of:

- Label ID
- Article number(s) or GTIN
- Name of the template file

**Note**: Only one matching per label is allowed but articles may be matched to more than one label.

Select File – New matchings to open the dialog where you can select the desired data records and create a number of matchings at the same time. To generate a multi-matching, multiple article numbers separated with a comma have to be specified. Keep in mind that your template has to be able to render a image for multiple articles.




FIGURE 1-27: New matchings dialog

Another way to create/edit matchings is under "Matchings – All Matchings":

- Select the desired data records (Label ID, Article Number) in the following window "New Matching Record" (either manually or with the magnifying glass symbol). Select an appropriate template via "Template" that should be used to generate the image.
- Confirm your choice by clicking Save. After that, the generated image is sent to the selected label.




FIGURE 1-28: Create a matching



It's also possible to create Matchings with SES-imagotag Control Center under Labels and Articles, for this just select the desired article or label, right-click on it and select "New matching..." (the new matching dialog will be pre-filled with the article or label information).

# 11.5 Set (extended) filters for enums

There are various filter options. Besides the known filter options you'll now have the possibility to set extended filters. Enable/disable the extended filter as shown in image below.




FIGURE 1-29: Use and enable the extended filter mode

With the extended filter options it's possible to set and combine several filters. Click on the drop down menu to see the different choices.




FIGURE 1-30: SES-imagotag Control Center extended filter options

### 11.5.1 Extended filter operators

The following operators are available:





Operator	Description
<	Less than
>	Greater than
<=	Less than and equal
>=	Greater than and equal
!	Negation (Not)
=	Equals
:	Defines a range (e.g. RSSI filter -65:-75 shows all labels with current RSSI value within -65 and -75) Doesn't apply to date and text.



# 12 Templates

The template is used to specify the fields, which should be rendered into the image. The SES-imagotag Core Service can handle multiple templates.

# 12.1 General information about templates

The image rendering process is based on XSL (EXtensible Stylesheet Language) templates. The individual image for the label is then generated by applying the template to a XML, which is based on the properties of the label and is expanded by a custom XML from the user.

The following steps are executed when processing a template:

- Generating a record XML based on the label/task information and custom information provided by the user
- Applying the template (XSL) on the generated record XML. This results in a document containing the fields, specified in this reference and values referenced from the XML
- Rendering the image (\*.PNG) based on the previous output



FIGURE 1-31: Input and result of the rendering process

# 12.2 SES-imagotag Template Editor

In order to use our rendering engine you must know our template language which is basically XSL. We do also have a SES-imagotag Template Editor with live preview, but you need a little bit time to setup everything and get familiar with it. Therefore we suggest to send pre-rendered images to labels (right-click on a label -> send image) which you can create with every image manipulation software you want (e.g. Gimp, Photoshop, Paint, ...). You can even take some pre-rendered images from us for each label type with the correct resolution as a template – you'll find some in the SES-imagotag Control Center's directory under data/images.

### 12.2.1 Starting SES-imagotag Template Editor

Navigate to the unpacked SES-imagotag Template Editor (see point *Get the latest software and documentation* on how to unpack the software package) and execute the "template.jar" file (see *Troubleshooting* on page 36).






FIGURE 1-32: Starting the SES-imagotag Template Editor

### 12.2.2 Open default template file and load records from server:

- Open the SES-imagotag Template Editor by clicking the "template.jar" file located in the template-directory (In our example it should be C:\imagotag\teamplate\).
- Next step is to create a new template file or to open an existing one (The default.xsl template file is located in the server-directory under C:\imagotag\server\data\template\).
- To get a live preview you'll have to load some records, in our case we load the demo article records from our running server, see the following figure.



FIGURE 1-33: Load Records from Server



After these steps your SES-imagotag Template Editor window should look something like this:




FIGURE 1-34: SES-imagotag Template Editor with loaded records from server and default.xsI template file

### 12.2.3 Design Mode

You can enable the graphical mode of the SES-imagotag Template Editor by selecting **Settings – Configuration** – tick **Enable Design Mode** and finally the Save-button. The Design Mode can be used for creating very simple templates. If you want to use for example conditions in your template, you cannot use the design mode and you should start from zero without the design mode of the SES-imagotag Template Editor.




FIGURE 1-35: Enable Design Mode in SES-imagotag Template Editor

After enabling the Design Mode a new tab will show up.




FIGURE 1-36: SES-imagotag Template Editor Design Tab

### 12.2.4 Enable and show color red

As there are label types which are capable of showing the color "red" there's a short description how to enable this inside the xsl template file.

- Add colors option to image tag:
   <image width="XXX" height="XXX" colors="true" font-family="XXX">

### 12.2.5 Help Content

There's a link to the Help content for the SES-imagotag Template Editor, open it by clicking Help – Help Content in the SES-imagotag Template Editor or open the file index.html located in C:\imagotag\template\help\.

Also you can find further information on the USB Stick under **Documentation - Image Rendering** Reference.



# 13 Integration

# 13.1 Webservice integration

The SES-imagotag Core Service provides access to its interfaces methods through a RESTful web service API. The web service is designed according to the "Representational State Transfer" (REST) architectural pattern.

The SES-imagotag Core Service listens for incoming HTTP web service requests on the TCP port 8001 by default.

You can find further information and documentation about the webservice integration online under <a href="https://portal.imagotag.com/get/documentation">https://portal.imagotag.com/get/documentation</a>

### 13.2 Plugins

We provide several plug ins which are used for importing article information into the SES-imagotag Core Service.

You can find further information and documentation about our integration plugins online under https://portal.imagotag.com/get/documentation

## 13.3 Custom integration

For custom integration we provide a Plugin-Interface. Software development service is available from SES-imagotag software development team or third-party integration partners.

For pricing get in touch with our sales team (sales.at@ses-imagotag.com).



# 14 Troubleshooting

If you run into any errors during connecting or sending images to labels, please refer to the documentation included in the SES-imagotag Core Service. This documentation can be found in the AP-2010 web UI of the SES-imagotag Core Service under "Documentation".

- For problems updating the labels (error code column in labels window) refer to "Update Error Codes" or (task status column in labels window) refer to "Task Status"
- For connection status problems refer to "Connection Status"
- For label hardware errors (label error column in labels window) refer to "Label Error Codes"


Code	Problem	Solution
1	Label not licensed	The label is not licensed. Import the proper license file for the label or check for typos in the label id.
3	Label not registered	The label may have been deleted or has never been registered at all. Register label.
10	Image does not match display size	The size of the image does not match the label's display size. Please check the width and height of your image and look up the display size in pixels for the label. These sizes have to be equal.
11	Error during image rendering	Check template (wrong or faulty)
12	Error during image conversion	Change format of the image to standard format (e.g. PNG or BMP)
13	Invalid page	Page not supported by label type, choose a different page
14	Could not process task because there are unfinished tasks waiting for this label	Abort task or wait until unfinished tasks are finished
20	Template not found	Check template directory for missing template file
21	Error during template parsing	Correct template file (Invalid content found)
22	Error during content document creation	Check server and article record configuration
30	Could not send update because label has insufficient power to perform the update	The power status of the label is "Bad", which means it is very low on battery that in may not accomplish the display update. Replace the battery of the label.
62	HTTP communication error with the access point	The server was not able to send the task to the Access Point. Please make sure that the Access Point is not offline (System -> Access Point Status) and there is an established network connection between Access Point and Server.
63	Label authentication failed (wrong encryption key)	Unlock the label
64	Task was removed from pipeline because previous transmission was not finished in time	Resend the corresponding task(s)
80 92	Error while writing task to database Task type not supported	Check database connection Upgrade AP software to process this kind of task

# 14.1 SES-imagotag Core Service Dashboard

To get a better overview accross your complete ESL system you can use the dashboard of the SES-imagotag Core Service. All kind of helpful information is shown here. You'll find the dashboard under



### http://<core-service-ip>:<port>/service/dashboard.xml



# 14.2 Running the SES-imagotag Core Service as a background service

The SES-imagotag Core Service may be started as a normal application, but on a productive system it is usually required to have it automatically started without a user logged in. To achieve this the SES-imagotag Core Service can be registered as a Windows service. It is than started automatically without any graphics user interface.

To install the SES-imagotag Core Service as a Windows service the batch file **install\_service.bat** is provided. If this file is executed with administrator privileges (Right click – Run as Administrator) it will install the SES-imagotag Core Service installation from the same directory as a Windows service with the name ESL\_SERVICE.

The file uninstall\_service.bat will remove the Windows service if executed with administrator privileges.

If you have any problems regarding the background service:

- Check if you have installed the correct JAVA version corresponding to your system (x86/x64)
- If the SES-imagotag Core Service is already installed as a Windows service you have to uninstall it first (uninstall service.bat) and reinstall it again (install service.bat).

# 14.3 Where can get a demo/development license key?

Ask the <a href="mailto:support.at@ses-imagotag.com">support.at@ses-imagotag.com</a> or <a href="mailto:sales.at@ses-imagotag.com">sales.at@ses-imagotag.com</a> team for a demo/development license.

# 14.4 Deleting the demo articles

In order to prevent the example articles from being re-added to the server, go to "System - Configuration" and set the "importFixtures" variable to false. Note: Please do not use the "Smart Box Package" for productive installation.



### 14.5 Establish a network configuration when no DHCP is available – Step by step

- 1. Set a laptops Ethernet adapter to DHCP
- 2. Turn off all other network adapters (Wi-Fi)
- 3. Connect to the same network as the AP-2010 (use a common Ethernet cable to connect your device directly with the AP-2010)
- 4. Start local SES-imagotag Core Service on laptop
- 5. Use the SES-imagotag Control Center to connect to your local SES-imagotag Core Service
- 6. Under System Access Point Status the AP should be listed as discovered (after successful boot sequence may take up to 2 minutes)
  - Press F5 on your keyboard or the refresh button in the ESL client to refresh the access point status (the Client doesn't refresh the status automatically!)
- 7. One Column of the AP should now show the IP address
- 8. Open a browser, type in http://<discovered-ip>:8080 or
  - at the SES-imagotag Control Center perform a right click on the discovered access point – Open in browser – Maintenance – Status

**Note:** Restart your access point if discovering process takes more than 2 minutes.




FIGURE 1-37: Restart and Factory Defaults button

# 14.6 Access point discovering with Bonjour Services

You still got problems to find your ESL access point in your network? There's another workaround: You can use Apple's "Bonjour Print Services".

Download and install "Bonjour Print Services" for Windows (pre-installed under OSX):

http://support.apple.com/kb/DL999

**Note:** After installation there's no reboot required.

If the access point is connected directly to the system where the "Bonjour Service" is installed (or on a network with running "Bonjour Service") you can find the access point by typing the following in the browser of your choice:

http://ap-<ID>.local:8080 (e.g. http://ap-12724.local:8080)

**Note:** You can reach older versions of the AP with <a href="http://imagotag-ap.local:8080">http://imagotag-ap.local:8080</a> (custom hostnames are only available on newer versions of the access point)

### 14.7 What can I do if the Status LED of the AP-2010 access point doesn't turn blue?

- · Check the access point status
- · Check the access point configuration
  - No channel set
- Check network reachability of the access point



- Is the access point registered to the SES-imagotag Core Service?
- · Reboot the access point

### 14.8 Labels don't come online

After the registration it could last a certain time until all registered labels are joined to the network (up to two hours, depending on number of access points and the channels used.

- Up to 30 minutes with channels 3, 5, 8, 9 and 10
- Up to 2 hours with channels 0, 1, 2, 4, 6 and 7

Warning: A label must not be registered to multiple SES-imagotag Core Service installations at the same time. It will only connect to one of this installations.

### 14.9 The encryption does not work

Check the encryption passphrase via the SES-imagotag Control Center - System – Configuration.

If label was already registered with a different passphrase you'll have to unlock the label first in order to register it on the SES-imagotag Core Service.

### 14.10 Unlocking labels

If the label was registered and a communication key was set it will no longer work in other networks using a different network key passphrase. To unlock this labels for other networks an unlock code is required.

Select File - Unlock labels and enter the unlock key.

If you have any problems (the unlock code wasn't included or you can't find it) please contact the SES-imagotag Support Team (<a href="mailto:support.at@ses-imagotag.com">support.at@ses-imagotag.com</a>).

# 14.11 Starting Java applications

Before starting a Java application, make sure you have Java Runtime Environment Version 6 or higher installed and you have set the necessary environment variables.

If the .jar file extension is known and associated with Java, just double-click the jar file to start the application. Otherwise if the extension is not recognized:

### Windows:

Create a shortcut of the jar file, right-click on it and open properties. Prepend "javaw.exe –jar" to the path in the "Target" field. Double-click the shortcut.

### Linux:

Navigate via command line to the directory where the jar file lies and execute "java –jar <filename>.jar"

In case your environment variables are not set properly (e.g. javaw.exe/java command could not be found) do the following steps:

- 1. Locate your installation directory of your Java Runtime Environment
- 2. Set JAVA\_HOME Variable

### **Under Windows:**



- Right-click on "My Computer" and select "Properties"
- Click the advanced tab
- Click the "EnvironmentVariables" button
- Under "SystemVariables", click New.
- Enter the variable name as JAVA\_HOME
- Enter the variable value as the installation directory of your Java Runtime Environment
- Click OK
- Look for the Path variable in "SystemVariables" and edit it
- Append a semicolon (;) and %JAVA HOME%\bin to it
- Click OK
- ApplyChanges

### **Under Linux:**

- Use the "export" command to set your variables
   export JAVA\_HOME=<pathToJRE>
- export PATH=\$PATH:<pathToJRE>/bin
- In order to make these changes persistent, write them into your .bash\_profile file and use "source ~/.bash profile" to apply the changes

# 14.12 Encoding problems

Per default, UTF-8 encoding is used. If you have any problems regarding encoding you can force any java application to use UTF-8. By setting the (Windows) environment variable JAVA\_TOOL\_ **OPTIONS** to **-Dfile.encoding=UTF8**, the (Java) System property will be set automatically every time a JVM is started.


### 14.13 Reserve RAM for Java heap space

As the generation of PDFs in the Site Survey Tool might need a lot of memory (depending on the amount of measurements, uploaded pictures, ...) we recommend to use half of the available memory for the Site Survey Tool.

In this case, please start the Site Survey Tool via Command Line (or create a corresponding shortcut respectively batch file) with corresponding parameters.

If your notebook has 4 GB RAM, please reserve 2 GB for the Site Survey Tool with following command:

D:\Builds\sitesurvey>java -Xmx2g -jar sitesurvey.jar



### Example:

- · m for megabyte -Xmx512m



g for gigabyte -Xmx2g

The same method can be used to reserve memory for the SES-imagotag Core Service.

Detailed information regarding JAVA options: <a href="https://docs.oracle.com/cd/E13150\_01/jrockit\_jvm/jrockit/jrdocs/refman/optionX.html">https://docs.oracle.com/cd/E13150\_01/jrockit\_jvm/jrockit/jrdocs/refman/optionX.html</a>

### 14.14 Further documentation

Please visit <a href="https://portal.imagotag.com">https://portal.imagotag.com</a> for further documentation.



### 15 Declaration

### **USA**

It applies to the product: VUSION 1.6" (EDG2-0160-A), VUSION 2.2" (EDG2-0220-A, EDG3-0220-A), VUSION 2.2" F (EDG2-0220-A), VUSION 2.6" (EDG2-0260-A), VUSION 2.6" F (EDG2-0260-A), VUSION 2.7" (EDG2-0270-A, EDG2-0270-B), VUSION 3.7" (EDG2-0370-A), VUSION 4.2" (EDG2-0420-A), VUSION 4.5" (EDG2-0450-A), VUSION 5.9" (EDG2-0590-A), VUSION 7.4" (EDG2-0740-A), VUSION 9.7" (EDG2-0970-A), VUSION 12.2" (EDG2-1220-A)

Core Appliance

AP-2010 USA / Canada bundle incl. Antenna

### **FCC**

This device complies with part 15 of the FCC Rules. Operation is subject to the following two conditions: (1) This device may not cause harmful interference, and (2) this device must accept any interference received, including interference that may cause undesired operation.

Changes or modifications not expressly approved by the party responsible for compliance could void the authority to operate the equipment.

### **CANADA**

It applies to the product: VUSION 1.6" (EDG2-0160-A), VUSION 2.2" (EDG2-0220-A, EDG3-0220-A), VUSION 2.2" F (EDG2-0220-A), VUSION 2.6" (EDG2-0260-A), VUSION 2.6" F (EDG2-0260-A), VUSION 2.7" (EDG2-0270-A,EDG2-0270-B), VUSION 3.7" (EDG2-0370-A), VUSION 4.2" (EDG2-0420-A), VUSION 4.5" (EDG2-0450-A), VUSION 5.9" (EDG2-0590-A), VUSION 7.4" (EDG2-0740-A), VUSION 9.7" (EDG2-0970-A), VUSION 12.2" (EDG2-1220-A)

Core Appliance

AP-2010 USA / Canada bundle incl. Antenna

### IC

This device contains licence-exempt transmitter(s)/receiver(s) that comply withInnovation, Science and Economic Development Canada's licence-exempt RSS(s). Operation is subject to the following two conditions: (1) This device may not cause interference. (2) This device must accept any interference, including interference that may cause undesired operation of the device.

L'émetteur/récepteur exempt de licence contenu dans le présent appareil estconforme aux CNR d'Innovation, Sciences et Développement économique Canadaapplicables aux appareils radio exempts de licence. L'exploitation est autoriséeaux deux conditions suivantes: 1) L'appareil ne doit pas produire de brouillage; 2) L'appareil doit accepter tout brouillage radioélectrique subi, même si lebrouillage est susceptible d'en compromettre le fonctionnement.

### **Taiwan**





It applies to the product: VUSION 1.6" (EDG2-0160-A), VUSION 2.2" (EDG2-0220-A), VUSION 2.2" F (EDG2-0220-A), VUSION 2.6" (EDG2-0260-A), VUSION 2.6" F (EDG2-0260-A), VUSION 4.2" (EDG2-0420-A), VUSION 4.5" (EDG2-0450-A), VUSION 7.4" (EDG2-0740-A), VUSION 12.2" (EDG2-1220-A)

Core Appliance

AP-2010 bundle incl. Antenna

警語

經型式認證合格之低功率射頻電機,非經許可,公司、商號或使用者均不得擅自變更頻率、加大功率或變更原設計之特性及功能。

低功率射頻電機之使用不得影響飛航安全及干擾合法通信;經發現有干擾現象時,應立即停用

,並改善至無干擾時方得繼續使用。

前項合法通信,指依電信法規定作業之無線電通信。低功率射頻電機須忍受合法通信或工業、

科學及醫療用電波輻射性電機設備之干擾

### **South Korea**

It applies to the product: VUSION 1.6" (EDG2-0160-A), VUSION 2.2" (EDG2-0220-A), VUSION 2.2" F (EDG2-0220-A), VUSION 2.6" (EDG2-0260-A), VUSION 2.6" F (EDG2-0260-A), VUSION 4.2" (EDG2-0420-A), VUSION 4.5" (EDG2-0450-A), VUSION 7.4" (EDG2-0740-A)

AP-2010 bundle incl. Antenna

해당 무선설비는 전파혼신 가능성이 있으므로 인명안전과 관련된 서비스는 할 수 없음

**Singapore** 

EDG2-0160-A

EDG2-0220-A

Complies with IMDA Standards N1519-18

Complies with IMDA Standards N1522-18

EDG2-0260-A

EDG2-0420-A

EDG2-0740-A

Complies with IMDA Standards N1524-18

Complies with IMDA Standards N1527-18

Complies with IMDA Standards N1529-18



Core Appliance



# 16 Warning

### WARNING - KEEP BATTERIES OUT OF REACH OF CHILDREN

- Swallowing may lead to serious injury in as little as 2 hours or death, due to chemical burns and potential perforation of the oesophagus.
- If you suspect your child has swallowed or inserted a button battery immediately call local Poisons Information Authority, with contact information available on-line.
- Examine devices and make sure the battery compartment is correctly secured, e.g. that the screw or other mechanical fastener is tightened. Do not use if compartment is not secure.
- Dispose of used button batteries immediately and safely. Flat batteries can still be dangerous.
- Tell others about the risk associated with button batteries and how to keep their children safe.